



Seavus Project Viewer

The complete viewer for *Microsoft® Project* files

System Requirements

TABLE OF CONTENT

<u>1</u>	<u>SYSTEM REQUIREMENTS</u>	<u>3</u>
<u>2</u>	<u>LICENSE METERING</u>	<u>4</u>

1 SYSTEM REQUIREMENTS

To use the Seavus Project Viewer to read your Microsoft Project® files (.mpp) you will need the following:

Processor

Intel® Pentium II® or Pentium-grade processor, Celeron Processor or Athlon Processor.

Operating System

Microsoft Windows 7

Microsoft Windows Vista

Microsoft Windows 2000/Professional/Server Edition

Microsoft Windows XP Professional/Home Edition

Microsoft Windows Server 2003

Memory

Minimum of 128MB of RAM (256MB or higher recommended)

Hard Disk

Minimum of 20MB of available hard-disk space

Display

SVGA (800 × 600) or higher-resolution monitor

2 LICENSE METERING

Seavus Project Viewer has a built-in license metering module that helps you in avoiding any unintentional violation of our license agreement. Seavus Project Viewer can be licensed both as single-user or multi-user software and depending on your license, this license-metering module makes sure, that no more than the licensed number of users are using Seavus Project Viewer concurrently.

Single-user license

The single-user version of Seavus Project Viewer license is identified by a combination of a license key and a signature obtained through the activation process (see the "How to activate the product?" section for more details). You, i.e. your organization, may purchase a certain amount of single-user licenses and our activation server will enable you to use the purchased license key on multiple computers, up to the specified amount of licenses.

The signature obtained during the activation process bounds your single-user license to the hardware of your computer, so if you change your hardware or want to transfer the license to a different computer, you will need to reactivate the old license, as described in the "How to activate the product?" section.

Multi-user license

The multi-user version of Seavus Project Viewer license is also known as concurrent license. In order to use this license, your organization should use a licensing server from Seavus. This server is licensed through a multi-user license and activated first, before any Seavus Project Viewer application can be run. The multi-user license can be purchased for a certain amount of users which can concurrently (at the same time) run the product.

In the multi-user licensing model, no Seavus Project Viewer installation is required on the user's machine. The application is run from a network share, appointed by the administrator. This is done so that the user is spared the details of setting up a connection to the licensing server.

Once the application is started, it contacts the licensing server for permission to run. If the license metering in the licensing server finds out that the maximum limit of concurrently running users is not reached, you will be permitted to run the application and view project files.

If the limit has been reached, you will get a warning message and the application will close itself. If, in the meantime, another user using the application stops working with it, i.e. closes it, you can use Seavus Project Viewer, since the license metering system will put the license used by the closed application back to the unused licenses, thus other users can freely use it.

Seavus Group
Skeppsbron 5
211 10 Malmö, Sweden
Phone: + 46 (0) 40-300-940
Fax: + 46 (0) 40-300-941
Email: support@seavusprojectviewer.com
URL: www.seavusprojectviewer.com

All documents prepared or furnished by Seavus Group and the copyright therein shall remain the property of Seavus Group.

Photo: Foto Spring